M-Hance/Trinity upgrades

You can download the installation/upgrade packages from our website at http://www.dynavistics.com/downloads. Just fill out the short form and the page will refresh to show available downloads.

The most common mistake on the installation/upgrade is missing the part that you need to use a 64 bit ODBC for the installer. Please pay special attention to that in the installation/upgrade documentation.

Upgrade Paths

Current Version	Step to	Final version
GP 2015 R2 with Trinity 14.0.1	None	GP 2016 R2 with Trinity 16.2.28
GP 2015 RTM with Trinity 14.0.0	GP 2015 R2 with Trinity 14.0.1	GP 2016 R2 with Trinity 16.2.28
GP 2013 R2 with Trinity 12.0.4	None	GP 2016 R2 with Trinity 16.2.28
GP 2013 SP2 with Trinity 12.0.2	GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28
GP 2013 12.00.1826 or later with Myridas 12.0.4 If GP lower than 12.00.1826 with Myridas 12.0.3	None GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28 GP 2016 R2 with Trinity 16.2.28
GP 2010 with Trinity 11.0.4 or above	GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28
GP2010 R2 (sp2) with Trinity 11.0.1	GP2010 with sp3 with Trinity 11.0.5 GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28
GP2010 R2 (sp2) with Trinity 11.0.2	GP2010 with sp3 with Trinity 11.0.5 GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28
GP2010 R2 (sp2) Trinity 11.0.3	GP2010 with sp3 with Trinity 11.0.5 GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28
GP2010 without service packs with Trinity 11.0.0	GP2010 with sp3 with Trinity 11.0.5 GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28
GP 10.0 with Trinity 10.0	GP2010 with sp3 with Trinity 11.0.5 GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28
GP 9.0 with Trinity 9.1	GP2010 with sp3 with Trinity 11.0.5 GP 2013 R2 with Trinity 12.0.4	GP 2016 R2 with Trinity 16.2.28